

Common Problems

- The intouch batch file on the terminal is just a blank box
- Print jobs are stuck spooling in the print queue
- Only Takeaway showing on the main screen
- Meal Deals keep disappearing
- The screen is upside down or turned on its side
- Internet order arriving doesn't make a sound

The intouch batch file on the terminal is just a blank box

The intouch batch file contains :-

```
@ECHO OFF
```

```
: TOP
```

```
IF EXIST \\server\c\winci\wcimain.exe (xcopy \\server\c\winci\data\*. * c:\winci\data\ /D /Y) ELSE  
GOTO TOP
```

```
IF EXIST \\server\c\winci\wcimain.exe (xcopy \\server\c\winci\audit\*. * c:\winci\audit\ /D /Y) ELSE  
GOTO TOP
```

```
IF EXIST \\server\c\winci\wcimain.exe (\\server\c\winci\wcimain.exe /s /f \\server\c\winci\ ) ELSE  
GOTO TOP
```

and is loop looking for \\server\c\winci\wcimain.exe and if it can't see this on the network the box will stay blank.

It can be one of a few things that you need to check on the Windows setup.

In network and sharing check that the network is set to private and if not in Windows 10 you can just click on it and change it. In Windows 10 if you go into settings>Network and Internet and click on Ethernet and then the name of the connection and change it to private from public.

Alternatively in Network and Sharing Centre click on Change advanced sharing on the top right and in Private Turn on network discovery and Turn on file and printer sharing. In All Networks set file Sharing to Enable file sharing for devices that use 40- or 56-bit encryption (This is if one of the terminals is XP as XP uses lower encryption) and Turn off password-protected sharing.

If none of this has worked Aaron found that if you try Editing the registry key

AllowInsecureGuestAuth

HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\LanmanWorkstation\Parameters

And changing the value to 1.








If it isn't there add it and restart.

Print jobs are stuck spooling in the print queue

If print jobs are stuck spooling in the print queue it could be the QR code files that need copying and registering.

The files are in the intouch folder on the fileserver and a folder called QR CODE FILES within it.

The contents of the folder should be what is in the image below.

 qrcode	26/09/19 15:01	Application	456 KB
 qrcode	24/05/21 11:23	Text Document	1 KB
 qrcode1	28/04/21 12:47	JPG File	8 KB
 reg	13/10/21 13:18	Windows Batch File	1 KB
 StrokeScribe.ocx	21/04/21 22:51	ActiveX control	5,812 KB
 StrokeScribeClass.dll	21/04/21 22:51	Application exten...	5,764 KB
 StrokeScribeDL.dll	21/04/21 22:52	Application exten...	5,628 KB

Copy the contents of this folder to the WINCI folder and then run the reg.bat file to register the files.

Only Takeaway showing on the main screen

This can be one of a couple of things.

Either the option in the security section of option is set to something other than "Delivery & Takeaway" or there is no customers file.

If you check the option in the security section of options in 2 at the bottom right you should see the following screen.

Receipt	Kitchen	Charges	Reports	Restaurant	Order Screen	Security	Set-Up
<div><div><div>Buttons</div><div>Order Types No Sale Log In Log Out Drivers Float Reprint Last Order Driver Log Assign Vehicles Assign to Kitchen (Deliveries) Shift Changes Call Log Colour <input type="checkbox"/> No Discount Button <input type="checkbox"/> Hides Print EOD Report Button <input type="checkbox"/> Allow Stock Control <input type="checkbox"/> Allow Wastage <input type="checkbox"/> Allow Raw Wastage <input checked="" type="checkbox"/> Driver Return <input type="checkbox"/> Hides No of Outstanding Orders <input type="checkbox"/> Purge Button on Main Menu <input type="checkbox"/> Stock/Waste on Main Menu <input type="checkbox"/> Expenses on Main Menu <input type="checkbox"/> Payment on Account <input type="checkbox"/> Drivers Log Includes Assistants for T/A <input type="checkbox"/> Logs Driver Out when Payment Made</div><div><div>Terminate Programs</div><div>None Opt 1 Opt 2 Opt 3</div></div></div><div><div>Passwords</div><div>if Discount More Than 0.00 % <input type="checkbox"/> Needed when Logging In/Out <input type="checkbox"/> Needed when Assigning to Driver</div><div>Loyalty Schemes</div><div><div>Earn</div><div>For Each £ 0 Receive - Points <input type="checkbox"/> 1 Point for Each Pizza</div><div>Display</div><div><input type="checkbox"/> Display for Take Away Display on No If More Than 0 Pts</div><div>Redeem</div><div>Free Pizza for 0 Points After 0 Points 0 Discount <input type="checkbox"/> Can Edit Loyalty Points <input type="checkbox"/> Cash & C/C Only</div><div>Edit Orders</div><div><input checked="" type="checkbox"/> Allow Edit Orders After Completion <input type="checkbox"/> No Edit Allowed After Assigned To Driver <input type="checkbox"/> Doesn't Store Amended Order Details <input type="checkbox"/> Always Allows Reprint Order <input type="checkbox"/> Stores All Quantity Reduced Items View Orders Yes <input type="checkbox"/> Edit Customer Options <input type="checkbox"/> Can't Change Payment Method after Finalising HO. Number 0</div></div></div></div>							

Abort

Save & Exit

1


2

Anything other than the top choice (Delivery & Takeaway) will get rid of Delivery. Assign to Driver

and Payment by Driver.

If this is OK the problem may be to do with the customer file. It can either be corrupt or has been damaged and is empty.

Try replacing it from either last nights backup or one of the older ones if that has the same problem.



Meal Deals keep disappearing

If the meal deals keep disappearing when they have been added it can be a problem with the wcibuttnd.dan file.

When this happens when you go into the meal deal everything is blank, like below, rather than with a new deal it is usually filled in with the price being 0.

Screen

Details

Mega Meal Deal

Price	Price 2	Just Eat Delivery	Just Eat Collect

Applies to

☐ Free Delivery

☐ Monday

☐ Tuesday

☐ Wednesday

☐ Thursday

☐ Friday

☐ Saturday

☐ Sunday

From:-

0

To:-

0

Add New Course

Quantity:-Toppings:-☐ Force Toppings☐ Force Instructions

Course 1

Pizza

Burgers, Veg, Chicken

Kebabs, Donner

Side Orders

Starters

Deserts, Drinks

A

B

C


D

E

F

Finished

To fix this delete the button that was setup, right click beneath the buttons in the grey space (Highlighted below) and re-enter the meal deal.


12"	12" Stuff Crust	12" Kebab Crust						
Margherita	Veg Supreme	Peri Peri Chicken	Chicken Tikka					
Keema	T's Special	Turkish Delight	Lamb Balti					
Donner Pizza	Pepperoni Passion	Seekh Kebab Pizza	Meat Feast					
								
Pizzas	Smash It & Basic Burger	Pak Pak & Peri Peri	Donner & Parmesans	Kids Meals & Sides	Drinks	Desserts		
A	B	C	D	E	F	G		
Finished	Toppings 1	Staff	Cooking Instructions	Reasons	Expenses	Raw Ingredients	Restaurant Tables	Meal Deals

The screen is upside down or turned on its side

A customer may call to say the display is either upside down or turned on its side.

If you login it may appear normal to you. This is usually a setting in the display driver and in the intel display driver there is a hotkeys setting that will do this if left enabled. If it is disabled it will prevent this happening in the future.

In the intel Display Driver somewhere will be a page similar to what is below.



If you disable the hot keys after changing the screen back to normal it should happen again.

The screen above may be different on different versions of Windows and different versions of the driver.

Internet order arriving doesn't make a sound

When internet orders arrive the system can make an intermittent sound to alert the staff there is an order there.

If the sound isn't being made there are a few things to check.

First make sure the beep.wav file is in the winci folder. If this isn't there you can get a copy in the intouch folder of the shared drive.

If the sound still isn't being played the speakers may be muted.

At the bottom right near the time on the Windows taskbar there should be a little speaker icon and this has a cross it is muted.

[image-1689449376181.png](#)

Image not found or type unknown

To unmute it click on it and click on the speaker to unmute.

[image-1689450278695.png](#)

Image not found or type unknown

Sometimes windows sets it to mute automatically when it starts up. To get around this there are a couple of files in the fileserver in the intouch folder in a folder called unmute. Copy the nircmd file to the Windows folder and the unmute batch file to the integer folder and make a shortcut to the batch file in start-up and this should make windows unmute on start-up.